

How to Delete Saved Passwords from Your Web Browser

If you automatically sign in to websites using stored credentials (username and password) in your web browser you may experience conflicts when you change a password but do not also save the new password to the list of saved passwords in your browser. Additionally, saved passwords are potentially a security risk because it becomes easier for third parties to access your saved login credentials stored in your web browser.

To Remove a Saved Password from Google Chrome (version 62)

Windows and macOS:

1. Click the three-dot menu icon in the top-right corner of the screen and select **Settings**.
2. Scroll down to the bottom of the page and click **Advanced**.
3. Scroll down further to **Passwords and forms** and select **Manage passwords**.
4. Under **Saved Passwords** look in the **Website** list for the website you would like to remove in order to remove the saved password from the browser.
5. Click on the three-dot, **More actions...** icon to the far right of the website name and select **Remove**.

Android:

1. Select the three-dot menu icon in the top-right corner of the screen and select **Settings**.
2. Under Basics select **Save passwords**.
3. Under Passwords select the website you would like to remove.
4. Select the trash icon on the top right of the screen to remove the saved website, username and password.

iPhone:

1. Select the three-dot menu icon in the top-right corner of the screen and tap on **Settings**.
2. Under Basics tap on **Save passwords**.
3. Tap **Edit** and tap on the entry/website you would like to remove.
4. Tap **Delete** at the bottom of the screen.

More information on [managing saved passwords from Google Chrome Help](#).

To Remove a Saved Password from Firefox

Windows and macOS (Firefox v56):

1. Select the three-bar menu button  in the top-right corner of the screen and choose **Options**.
2. Select the **Privacy & Security** panel from the list on the left side of the page.
3. Select **Saved Logins** under **Forms & Passwords**. The Saved Logins dialogue box will open.
4. To remove the username and password for a website, select the site's entry from the list and select **Remove**.

Android (Firefox v56):

1. Select the three-dot menu button in the top-right corner of the screen and choose **Settings**.
2. Select **Privacy** (tracking, logins data choices) from the list on the page.
3. Under Logins select **Manage logins**.
4. To remove the username and password for a website, select the site's entry from the list and select **Delete**.

iPhone: (Firefox v9.3)

1. Tap on the three-bar menu button  at the bottom middle of the screen and swipe left to the second page.
2. Tap on **Settings**.
3. Tap on **Logins** in the Privacy section.
4. Tap **Edit**
5. Tap on the entry you would like to remove.
6. Tap **Delete** on the top right of the screen.

More Information on [managing passwords in Firefox from Mozilla Support](#)

To Remove a Saved Password from Opera:

Windows (Opera version 48):

1. Open Opera and click the Opera **Menu** button in the upper left corner of the screen and select **Settings**.
2. Click on **Privacy & security** from the left panel.
3. Scroll down to **Passwords** and click on **Show all passwords**.
4. Under **Saved passwords** highlight the website with your username and password that you want to delete and click on the **X** to the right of the entry.

macOS (Opera version 48):

1. Open Opera select **Opera > Preferences** from the toolbar at the top of the screen and select **Settings**.
2. Click on **Privacy & security** from the left panel.
3. Under Passwords select **Show all passwords**.
4. Under **Saved passwords** highlight the website with your username and password that you want to delete and click on the **X** to the right of the entry.

Android (Opera version 43):

1. Open Opera and tap the Opera **Menu** button in the lower right corner of the screen and select the settings (gear) icon at the bottom middle of the screen.
2. Under Privacy tap Clear browsing data....
3. Select **Clear saved passwords** and tap **OK**
4. Opera will respond with "Data cleared."

iPhone (Opera version 16):

1. Open Opera and tap on the red **O** menu.
2. Tap on **Settings**.
3. Tap on **Clear**.
4. Tap on **Clear Saved passwords**.

5. Tap **Yes** to clear saved passwords.

To Remove a Saved Password from Internet Explorer (version 11)

Windows:

1. Open the **Tools** menu (gear icon) in the upper-right corner of the screen and select **Internet Options**
2. Select the **Content** (middle) tab.
3. Under **AutoComplete**, click **Settings**.
4. Click on **Manage Passwords**.
5. Click on the **Web Credentials Manager**.
6. Click on the drop down arrow for the website that you would like to remove in order to remove the saved password from the browser.
7. Click on **Remove**.

To Remove a Saved Password from Microsoft Edge

Windows:

1. Open Microsoft Edge and click on the **More Actions** button (this will appear as three dotted lines in the upper right corner of the screen).
2. Click on **Settings**.
3. Click on **View Advanced Settings** button.
4. Scroll down to find **Manage my saved passwords** and click on it to view all saved usernames and passwords.
5. To delete a specific password, click the **X** button next to the website URL.

More information on [managing saved passwords in Microsoft Edge from Lifewire.com](#)

To Remove a Saved Password from Safari (version 11):

macOS

1. Open Safari and select **Safari > Preferences** (from the toolbar at the top of the screen).
2. Select **Passwords**.
3. Click the **Edit** button for **Username and Passwords**.
4. Highlight the website that corresponds with your username and password that you want to delete, and select **Remove**.

iPhone (iOS 11)

1. Tap/Launch the **Settings** app for iOS 11
2. Scroll down and tap **Accounts & Passwords**.
3. Tap **App & Website Passwords**.
4. Authenticate using **Touch ID for "Settings"** if necessary and enter your passcode.
5. Tap the **Edit** button in the top-right corner of the screen and select any password entries you would like to remove, then tap **Delete**.

[Internet Browser General Information and How-Tos from Lifewire.com](#)